

MEDIATEK

INTERNAL USE

Basic Tuning Flow – Basic Info Calibration




Introduction to Optical Black (OB)

- Optical Black (OB)

- There may have offset in image raw data, caused by sensor dark current, would lead to incorrect color. As a result, the offset, named OB, should be calibrated and reduced through ISP


OB taken off not enough



OB taken off correctly



OB taken off too much




Introduction to Minimum Saturation Gain

■ Minimum Saturation Gain

- Minimum gain value can make sensor output saturated with enough exposure (R/G/B reach max.)
- To check relation between exposure and sensor output is linear before saturation

Minimum Saturation Gain = $\frac{\text{saturation output}}{\text{linear saturation output}}$




Introduction to Minimum Saturation Gain

■ Decline Rate

- Used to determine the linear saturation point. Larger decline rate gets larger linear saturation point

■ Gain Buffer

- Considering module difference, use a larger Saturation Gain to make sure every module can reach saturation
 - $\text{FinalMinSatGain} = \text{MinSatGain} * (1 + \text{GainBuffer})$



Introduction to Minimum ISO

➤ Minimum ISO

- The ISO value when gain is 1x (1024)
 - To test sensitivity of sensor

Use 1st Version Parameters

- Before tuning, merge 3A default setting to initial parameters

CDVT Sensor Test PreCheck

- To avoid brightness change led by Auto Focus, it's necessary to disable AF before calibration
- Adb command
 - `setprop debug.af_motor.disable 1`
 - `setprop debug.af_motor.position 1000`

CDVT sensor calibration

➤ Goal

- OB
 - Get mean value of OB of multiple test with the same sensitivity setting.
- Minimum ISO
 - Get ISO value with minimum sensor gain (1024)
- Minimum Saturation Gain
 - To find the minimum gain for sensor saturation (G channel)

➤ Use ISP_calibration_check_lists.xlsx to check result

Calibration Control

Mode : Preview

Run

OB

Exp time : 40000 us

Gain : 1024


Repeat : 10

Result :

CDVT sensor test – OB Stability

➤ Test flow

- Dark environment or cover lens with cloth.
- Select “Preview” mode.
- Select “OB Stability”.
- Set “Exp Time/Gain Start/Gain End/Gain Interval”.
- Click “Run” for testing.
- Result will be shown in “Analysis”.
- Click “Export” for output detail result.
- Repeat d,e,f,g for other modes.



➤ Expected result

- OB values of 4 channels can be different, but the difference can't be much within the same gain setting.

OB Calibration

■ Calibration condition

- Dark environment and cover lens.

■ Flow

- Set 'Expo time/Gain/Repeat times'.
- Click 'Run' for testing.
- Results as shown in test box.

CDVT Sensor Test CDVT Sensor Calibration Sensor Register Device Profile Shading

Calibration Control

Mode : Capture

Run

Calibration Mode

☒ OB

☐ Minimum ISO

☐ Minimum Saturation Gain

OB

Exp time : 40000 us

Gain : 1024

Repeat : 10

Result : 64

Minimum ISO

Mode

☐ 50 Hz ☒ 60 Hz

LV : 90

F number : 28

OB : 64

Result :

Check Calibration Results

- Expected result
 - OB values@10-bit of 4 channels should be same.
 - A little difference is acceptable(1~2 @10-bit)
 - OB values@10-bit of different ISO should be same.
- If something goes wrong,
 - Highlight to customer and vendor.

Code Setting

■ Path

- vendor\mediatek\proprietary\custom\\${project}\hal\imgsensor\ver2\\${sensor}\

■ File

- Camera_isp_regs_video_\${sensor}.h
- Camera_isp_regs_preview_\${sensor}.h
- Camera_isp_regs_capture_\${sensor}.h
- Camera_isp_regs_feature_\${sensor}.h

camera_isp_regs_\${scenario}_\${sensor}.h

```
#define OBC_0125 /*profile = N3D_Preview, ISO_3*/{ {\
    .offst0    = {.bits={.OBC_OFST_B=7936, .rsv_13=0}}, \
    .offst1    = {.bits={.OBC_OFST_GR=7936, .rsv_13=0}}, \
    .offst2    = {.bits={.OBC_OFST_GB=7936, .rsv_13=0}}, \
    .offst3    = {.bits={.OBC_OFST_R=7936, .rsv_13=0}}, \
    .gain0     = {.bits={.OBC_GAIN_B=546, .rsv_13=0}}, \
    .gain1     = {.bits={.OBC_GAIN_GR=546, .rsv_13=0}}, \
    .gain2     = {.bits={.OBC_GAIN_GB=546, .rsv_13=0}}, \
    .gain3     = {.bits={.OBC_GAIN_R=546, .rsv_13=0}} \
} \
} \
#define OBC_0126 /*profile = N3D_Preview, ISO_10*/{ {\
    .offst0    = {.bits={.OBC_OFST_B=7938, .rsv_13=0}}, \
    .offst1    = {.bits={.OBC_OFST_GR=7938, .rsv_13=0}}, \
    .offst2    = {.bits={.OBC_OFST_GB=7938, .rsv_13=0}}, \
    .offst3    = {.bits={.OBC_OFST_R=7938, .rsv_13=0}}, \
    .gain0     = {.bits={.OBC_GAIN_B=546, .rsv_13=0}}, \
    .gain1     = {.bits={.OBC_GAIN_GR=546, .rsv_13=0}}, \
    .gain2     = {.bits={.OBC_GAIN_GB=546, .rsv_13=0}}, \
    .gain3     = {.bits={.OBC_GAIN_R=546, .rsv_13=0}} \
} \
} \
}
```

we suggest use **CCT** to fill in OB value,
then tool would transform OB value to
Gain & Offset


Min Gain Calibration Flow

■ Calibration condition

- Camera face to a uniform light source.
- Connect to CCT Tool.
- Set maximum exposure time to 300 msec.


■ Calibration Flow

- a) Verify min gain = 1024.
- b) Min gain calibration.
- c) Check saturation status.
- d) Check result



Verify Min Gain = 1024

- Capture condition
 - Uniform light source.
- Test flow
 - same with Exposure Linearity.
- Check point
 - R/G/B can exceed 1024.
- If result is fail, highlight to customer in advance.



Verify min
gain = 1024

NG

Min. gain
calibration

Check sat.
status

Check result

Min. Gain Calibration

■ Test flow

- Average light source.
- Set 'Decline Rate/Gain Buffer/OB'.
- Click 'Run' to testing.
- Result as shown in text box.

The screenshot displays the 'CDVT Sensor Calibration' window with several tabs: 'CDVT Sensor Test', 'CDVT Sensor Calibration', 'Sensor Register', 'Device Profile', 'Shading Calibration', 'AE P-line Calibration', and 'AE Cali'. The 'CDVT Sensor Calibration' tab is active, showing three calibration modes: 'OB', 'Minimum ISO', and 'Minimum Saturation Gain'. The 'Minimum Saturation Gain' mode is selected, indicated by a blue radio button. The 'Mode' dropdown is set to 'Capture', and the 'Run' button is highlighted with a red box. The 'Minimum Saturation Gain' section is highlighted with a green box, showing the following settings: Mode (50 Hz), Decline rate (10%), Gain buffer (5%), OB (64), and Result (empty). Other sections like 'OB' and 'Minimum ISO' also show their respective settings.

Verify min
gain = 1024

NG



Min. gain
calibration

Check sat.
status

Check result


Check Saturation Status

- Check if R/G/B can exceed 1024.



Check Result

- If R/G/B can not exceed saturation region
 - Increase Gain margin.
 - Re-do min gain calibration.
 - Feedback to customer/sensor vendor



Verify min
gain = 1024

NG

Min. gain
calibration

Check sat.
status

Check result

Code Setting

- Path
 - vendor\mediatek\proprietary\custom\\${project}\hal\imgsensor\ver2\\${sensor}\AE_Tuning_Para
- Writing setting into following file
 - \$camera_ae_tuning_para_\${sensor}.cpp
 - \$camera_ae_tuning_para_cus1_\${sensor}.cpp
 - \$camera_ae_tuning_para_cus2_\${sensor}.cpp
 - \$camera_ae_tuning_para_cus4_\${sensor}.cpp
 - \$camera_ae_tuning_para_vdo_\${sensor}.cpp
 - \$camera_ae_tuning_para_pv_\${sensor}.cpp
 - \$camera_ae_tuning_para_cap_\${sensor}.cpp

camera_AE_tuning_para_\${scenario}_\${sensor}.cpp

```
#include "camera_custom_nvram.h"
#include "camera_ae_tuning_para_imx338mipiraw.h"

template <>
AE_NVRAM_T const&
getAENVRAM_imx338mipiraw<CAM_SCENARIO_CAPTURE>()
{
    // rDevicesInfo
    static AE_DEVICES_INFO_T g_rDevicesInfo =
    {
        1136, // u4MinGain
        8192, // u4MaxGain
        100, // u4MinISOGain
        16, // u4GainStepUnit
        13701, // u4PreExpUnit
        31, // u4PreMaxFrameRate
        10045, // u4VideoExpUnit
        30, // u4VideoMaxFrameRate
        1024, // u4Video2PreRatio
    }
```

➤ Fill the result into "DeviceInfo"

LensPartNum	FM50AFAP
u4LensFno	22
SensorPartNum	IMX135MIPIR
u4OBLevel	64
u4MinGain	1136

Minimum ISO

➤ Test flow

- a) Check whether F numver(LensFno) is correct
- b) Average light source , select correct light mode
- c) Set “Mode/LV(80~100)/F number/OB”.
- d) Click “Run” for testing.
- e) Result as shown in text box.

Minimum ISO

a Mode ☒ 50 Hz ☐ 60 Hz

b LV : 80

F number : 28

c OB : 64

d Result : 73

➤ Fill the result into “DeviceInfo”

u4MiniISOGain

51